32

NEON TOKYO

LIGHTROOM PRESETS AND LUTS

Neon Tokyo
Installation Guide

Table of Contents

Need Help?
Web form: www.sparklestock.com/contact
Email: support@sparklestock.com

Lightroom CC/Mobile
Installation Instructions

Step 1:

*In Lightroom CC, press **E** to open the Edit panel.*

Step 2:

Near the bottom of the interface, click on Presets.

Step 3:

*Click on the panel menu and select **Import Presets**.*


Step 4:

*Navigate to the folder where you've extracted the files. Load the **Lightroom CC\SparkleStock Neon Tokyo.zip** file.*

Step 5:

*Expand the **SparkleStock Neon Tokyo** folder and select a preset.*

Step 6:

To adjust the opacity, click on the"Browse Profiles" button in the Edit panel.

Adjust the amount slider located below the selected profile.

Sync to Lightroom iOS/Android/Web

After loading the presets to Lightroom CC, they will automatically sync to Lightroom on your mobile device. You must have an active Creative Cloud subscription.

Lightroom Classic CC
Installation Instructions

Step 1:

In Lightroom Classic CC, press **Ctrl+Alt+2** *(Macs:* **Cmd+Option+2***) to go to the Develop module.*

Step 2:

On the left side, open the Presets panel. Click on the **+** *button then choose* **Import Presets***.*

Step 3:

Navigate to the folder where you've extracted the files. Load the **Lightroom Classic CC\SparkleStock Neon Tokyo. zip** *file.*

Step 4:

Expand the **SparkleStock Neon Tokyo** *folder and select a preset.*

Step 5:

To adjust the opacity, adjust the **Amount** *slider inside the Basic panel.*

Photoshop CC (Camera Raw) Installation Instructions

Step 1:

Copy the **Photoshop CC\SparkleStock** *folder to the following locations:*

Mac:
~/Library/Application Support/Adobe/CameraRaw/Settings

Windows:
C:\ProgramData\Adobe\CameraRaw\Settings

Step 2:

Restart Photoshop CC.

Step 3:

In Photoshop CC, go to **Filter > Camera Raw**.

Step 4:

Go to the **Presets panel**.

Step 5:

Expand the **SparkleStock Neon Tokyo** *folder and select a preset.*